

How to Configure Eudora for yourdomainname.com E-mail

Email Type:
@yourdomainname.com




Use this document if:

- You need to configure Eudora 7 for yourdomainname.com e-mail.


This document assumes:

- You know your yourdomainname.com e-mail username and password.
- You have a working copy of Eudora 7.
- You have a working Internet connection.

This document only applies to Eudora 7.1. To find out what version you are using, select **Help** then **About Eudora**.




This will bring up the 'About' screen. Select the **Close** button after finding the Eudora Version. If the 'About' screen looks like the one below, continue reading.



1. Open Eudora using the icon on your desktop or Start menu.



2. Select **Tools**, then **Options**.



3. Select **Getting Started** on the left. Enter your **Real name**. This is the name that people see when you send them an email.




The screenshot shows a window titled "Options" with a dark header bar containing a question mark and a close button. Below the header, there is a "Category:" label and a list of categories. The "Getting Started" category, which features a coffee cup icon, is highlighted with a red rectangular border. To the right of the category list is a "Real name:" label and a text input field containing the text "Qwest Customer".

4. Enter your **Email address**.




The screenshot shows a form field labeled "Email address:". Below the label is a text input box containing the text "customer@yourdomainname.com".

5. Enter your **Mail Server (Incoming)** and **SMTP Server (Outgoing)**. Refer to the list at the end of this document.




The screenshot shows a form field labeled "Mail Server (Incoming):". Below the label is a text input box containing the text "pop.XXXXX.qwest.net".




The screenshot shows a form field labeled "SMTP Server (Outgoing):". Below the label is a text input box containing the text "pop.XXXXX.qwest.net". Below the input box is a checkbox labeled "Allow authentication" which is checked.

6. Enter your **User Name**. This is NOT the same as your email address.




The screenshot shows a form field labeled "User Name:". Below the label is a text input box containing the text "customer@qwest.net".

7. Select **Incoming Mail**. Place a checkmark next to:
 - **Leave mail on server** and
 - **Delete from server when emptied from Trash.**




8. Select **OK**.



9. Select the Check Mail icon.



10. In the Password field, type your password (passwords are CaSe sEnSiTiVe) and select **OK**. If you want Eudora to remember your password in the future, check the **Remember password for this personality** box.



11. Congratulations, you have configured Eudora 7 for your yourdomainname.com e-mail.



Qwest Mail Servers

Arizona

- Tucson- pop.tcsn.qwest.net
- Phoenix- pop.phnx.qwest.net

Colorado

- Colorado Springs- pop.clsp.qwest.net
- Denver- pop.dnvr.qwest.net

Idaho

- Boise- pop.bois.qwest.net

Iowa

- Des Moines- pop.desm.qwest.net
- Cedar Rapids- pop.cdrr.qwest.net
- Davenport- pop.dvnp.qwest.net

Minnesota

- Duluth- pop.dlth.qwest.net
- Minneapolis/St. Paul- pop.mpls.qwest.net
- Rochester- pop.roch.qwest.net
- Saint Cloud- pop.stcd.qwest.net

Montana

- Billings- pop.blng.qwest.net
- Missoula- pop.mssl.qwest.net

Nebraska

- Omaha- pop.omah.qwest.net

New Mexico

- Albuquerque- pop.albq.qwest.net

North Dakota

- Bismarck- pop.bsmr.qwest.net
- Fargo- pop.farg.qwest.net

Oregon

- Eugene- pop.eugn.qwest.net
- Portland- pop.ptld.qwest.net

South Dakota

- Sioux Falls- pop.sxfl.qwest.net

Utah

- Salt Lake City- pop.slkc.qwest.net

Washington

- Seattle- pop.sttl.qwest.net
- Spokane- pop.spkn.qwest.net

Wyoming

- Cheyenne- pop.chyn.qwest.net